
## **How to activate software license with Netgear managed switches?**

Some of the Netgear managed switches support licensed feature to add additional functionalities to the switch.


When you purchase a software license, you will receive an email with a license key. If you have not received an email with the license key, please contact your place of purchase or Netgear Technical Support to obtain the license key before proceeding further.

If you have a license key, follow the steps below to activate your license.


- 1. To activate the license, the switch must be first registered at <a href="http://my.netgear.com">http://my.netgear.com</a>.
- 2. Login using your existing account or register a new account.
- 3. After logged into the Netgear Service Portal, select "Register New Product" if the switch has not been registered or "My Registered Product" if the switch has been registered previously.




4. If the product has not been registered, enter the serial number, purchase date and place of purchase to register the product.



5. After registered the switch, select "My Registered Products", a list of registered products will be displayed. Click on "Activate license key for registered product" button. A new window will be opened with a list of registered products that support license upgrade.




6. Click on "Activate" next to the product you wish to activate the license key. A new window will be opened. The serial number field will be automatically filled out. Copy the license key from the software license email into the license key field and click "Submit".




7. If that is successful, a Download button will appear. Click on the Download button to download the license file. Save the file in a folder on your computer. You will need to download this license file into the switch to activate the licensed features. You can always download license file again


in the future by logging into <a href="https://my.netgear.com">https://my.netgear.com</a>, select "My Registered Products" and click on the "Activate license key for registered product" button.



8. With the license file, now you will need to download the license file into the switch. You can do that via the web GUI. Open the web GUI with the IP address of the switch. Select Maintenance->Download->HTTP File Download. Select "License key" as the File Type and select the license file from the folder where it was saved. Click Apply. You will get the message "License file download through HTTP is completed successfully" when transfer is completed.



9. Reload the switch to activate the license. You can reload the switch from the web GUI Maintenance->Reset->Device Reboot.



10. After the switch is rebooted. You can confirm the license have been activated from the web GUI System->License->License Key.

